ARTech Laboratory, Inc. Checklist for AE & BE Passives & Myos

AE or BE Passives
Lab plaster (not plaster bandage) model of "sound" hand with fingers in a relaxed or natural
position. Model should be 3-4 inches past the styloid.
Work Order with measurements and color choices completed.
Measurement from shortest or lowest point on socket opening to the tip of the thumb.
Socket with inner hand or "paddle" (2" wide, 3" long, 34" thick is best) attached. Need approx. 3
weeks after we receive the hand impression. If foam is required, please have that done at central fab. We
will need the mechanical the hand to set inside the silicone hand prior to being joined to the socket.
Color-true photos taken on our color background (available on our web site @ www.artechlab-
<u>prosthetics.com</u>). Photos should include palmer and dorsal of "sound" hand, a close up of the nails
(without polish), and underside and outer side of forearm and upper arm. You may refer to "Photo and
Model Policy", also available on our web site. Photos are needed up-front since we need a "base" color
(the lightest color, most usually on the palm of the hand, to color the silicone.
AE or BE Myos
Lab plaster (not plaster bandage) model of "sound" hand. Model should be 3-4 inches past styloid
Electronic hand (so we can make sure we sculpt to accommodate). Wrist rotator notation or other
info we might need to know.
Measurements & color choices filled out on Work Order .
Color choices, with patient input, filled out on Work Order .
Color-true photos taken on our color background (available on our web site @ www.artechlab-
<u>prosthetics.com</u>). Photos should include palmer and dorsal of "sound" hand, a close up of the nails
(without polish), and underside and outer side of forearm and upper arm. You may refer to "Photo and
Model Policy", also available on our web site. Photos are needed up-front since we need a "base" color
(the lightest color, most usually on the palm of the hand, to color the silicone.
Socket and mechanical needed approx. 3 weeks after we receive the hand model. "Skin" will be
applied over whatever type socket you send to us. <u>If foam is required</u> , please have that done at central
fab. We will need the mechanical the hand to set inside the silicone hand prior to being joined to the
socket.